DEVICE SETUP GUIDE

Connect ATAK or iTAK

Create a personal setup bundle in RallyTAK, provide it securely to one person or device, and import it into ATAK or iTAK.

> **KEEP THE SETUP ZIP PRIVATE**
>
> Each bundle contains one identity and its certificate. Give it only to the intended person, never post it in a group chat, and create a separate identity for every device.

FOR RALLYTAK OWNERS AND TEAM LEADS

You do not need to enter ports, certificates, usernames, or server addresses by hand. The setup bundle contains the connection and identity material the app needs.

SETUP ZIP

Create and download a setup ZIP

Create a separate identity for each person or device, then generate its setup ZIP from your RallyTAK service.

ONE IDENTITY PER DEVICE Use a named identity for normal devices. Avoid the built-in admin identity because its shared access cannot be revoked independently.

1

Open People & devices

Open your RallyTAK service and select Connect a device, or open the People & devices section.

2

Create the identity

Under Add one person or device, enter a name you will recognise. The WebTAK password is optional. Leave administrator access off for normal users, then select Create identity.

3

Create the setup ZIP

Find the new identity under Existing identities and select Create setup ZIP. For several people, expand Add several people or devices at once and enter one identity name per line.

4

Download it now

On the Setup ZIP ready page, select Download setup ZIP. The link is short-lived and normally works once. If it expires or the file is lost, create a new ZIP for the same identity.

5

Keep it intact and private

Do not unzip the file. Send it directly to the intended person or move it to the intended device using a private transfer method.

ATAK ON ANDROID

Set up ATAK on Android

Move the downloaded setup ZIP to the Android device, then use ATAK's built-in Import Manager.

> **DO NOT UNZIP THE FILE** Leave the provided setup ZIP intact. ATAK reads the server settings and certificate directly from it.

1

Save the setup ZIP

Download or transfer the intended identity's setup ZIP to the Android device and keep it in Download or Downloads.

2

Open Import Manager

In ATAK, open the main menu, choose Import Manager, then choose Local SD.

3

Select the ZIP

Open Download or Downloads, select the RallyTAK setup ZIP, and choose Data Package if ATAK asks how to handle it.

4

Enable the imported server

Open Settings > Network Preferences > TAK Servers. Find the imported server and make sure the connection is enabled.

5

Confirm the connection

Return to the map and wait for the connection indicator. Your marker and other connected team members will appear as positions update.

ITAK ON IPHONE AND IPAD

Set up iTAK on iPhone and iPad

Move the downloaded setup ZIP to Files, then import it from iTAK's server settings.

> **DO NOT UNZIP THE FILE** Keep the ZIP in Files until iTAK confirms the server has been added. Do not tap it in Files to extract it.

1. **Save the setup ZIP**

   Download or transfer the intended identity's setup ZIP to the device and keep it in Files > Downloads.

2. **Open server settings**

   In iTAK, tap the Settings cog, then open Network > Servers.

3. **Upload the server package**

   Tap +, choose Upload Server Package, then browse to the setup ZIP in the Files picker.

4. **Select the imported server**

   Choose the RallyTAK setup ZIP. If iTAK asks which connection to use, choose the newly imported server.

5. **Confirm the connection**

   Remain in Network > Servers until the imported server shows connected, then return to the map.