DEVICE SETUP GUIDE

Connect ATAK or iTAK

Use the personal RallyTAK setup bundle supplied by your team lead, event organiser, or server owner to connect ATAK or iTAK.

> **KEEP THE SETUP ZIP PRIVATE**
>
> The bundle is personal to you or your device. Do not forward it, post it in a group chat, reuse somebody else's bundle, or extract its contents.

FOR FRIENDS AND TEAM MEMBERS

You do not need to enter ports, certificates, usernames, or server addresses by hand. The setup bundle contains the connection and identity material the app needs.

ATAK ON ANDROID

Set up ATAK on Android

Save the setup bundle you were given in Downloads, then import it through ATAK.

> **DO NOT UNZIP THE FILE** Do not open the ZIP with an archive app. Import it from inside ATAK so the certificate and server settings stay together.

1

Save the provided bundle

Download or transfer the setup ZIP to your device and keep it in Download or Downloads.

2

Open Import Manager

In ATAK, open the main menu, choose Import Manager, then choose Local SD.

3

Select the ZIP

Open Download or Downloads, select the RallyTAK setup ZIP, and choose Data Package if ATAK asks how to handle it.

4

Enable the imported server

Open Settings > Network Preferences > TAK Servers. Find the imported server and make sure the connection is enabled.

5

Confirm the connection

Return to the map and wait for the connection indicator. If it does not connect, contact the person who supplied your bundle.

ITAK ON IPHONE AND IPAD

Set up iTAK on iPhone and iPad

Save the provided setup bundle in Files, then import it from iTAK's server settings.

> **DO NOT UNZIP THE FILE** Do not tap the ZIP in Files to extract it. Select the intact bundle from iTAK's file picker.

1. **Save the provided bundle**

   Download or transfer the setup ZIP to your device and keep it in Files > Downloads.

2. **Open server settings**

   In iTAK, tap the Settings cog, then open Network > Servers.

3. **Upload the server package**

   Tap +, choose Upload Server Package, then browse to Downloads in the Files picker.

4. **Select the setup ZIP**

   Choose the RallyTAK setup ZIP. If iTAK asks which connection to use, choose the newly imported server.

5. **Confirm the connection**

   Wait for the imported server to show connected, then return to the map. Contact the bundle provider if it remains disconnected.